

# User Manual

for MPC5634M ICU Driver

Document Number: UM14ICUASR3.0R2.0.0

Rev. 2.0





# Contents

Section Number	Title	Page
<b>Chapter 1</b>		
<b>Revision History</b>		
<b>Chapter 2</b>		
<b>Introduction</b>		
2.1	Supported Derivatives.....	11
2.2	Overview.....	11
2.3	About this Manual.....	12
2.4	Acronyms and Definitions.....	12
2.5	Reference List.....	13
<b>Chapter 3</b>		
<b>Driver</b>		
3.1	Requirements.....	15
3.2	Driver Design Sumary.....	15
3.3	Hardware channel availability.....	15
3.4	Additional Requirements and Deviations.....	16
3.5	Function Definitions.....	18
3.5.1	Function Icu_Init.....	18
3.5.2	Function Icu_DeInit.....	19
3.5.3	Function Icu_SetMode.....	19
3.5.4	Function Icu_SetClockMode.....	20
3.5.5	Function Icu_DisableWakeup.....	20
3.5.6	Function Icu_EnableWakeup.....	21
3.5.7	Function Icu_SetActivationCondition.....	21
3.5.8	Function Icu_DisableNotification.....	22
3.5.9	Function Icu_EnableNotification.....	22
3.5.10	Function Icu_GetInputState.....	23
3.5.11	Function Icu_StartTimestamp.....	23
3.5.12	Function Icu_StopTimestamp.....	24

Section Number	Title	Page
3.5.13	Function Icu_GetTimestampIndex.....	24
3.5.14	Function Icu_ResetEdgeCount.....	25
3.5.15	Function Icu_EnableEdgeCount.....	25
3.5.16	Function Icu_DisableEdgeCount.....	26
3.5.17	Function Icu_GetEdgeNumbers.....	26
3.5.18	Function Icu_StartSignalMeasurement.....	27
3.5.19	Function Icu_StopSignalMeasurement.....	27
3.5.20	Function Icu_GetTimeElapsed.....	28
3.5.21	Function Icu_GetDutyCycleValues.....	29
3.5.22	Function Icu_GetVersionInfo.....	29
3.6	Structure Definitions.....	30
3.6.1	Structure Icu_ConfigType.....	30
3.6.2	Structure Icu_ChannelConfigType.....	31
3.6.3	Structure Icu_DutyCycleType.....	32
3.7	Enum Definitions.....	32
3.7.1	Enumeration Icu_SelectPrescalerType.....	32
3.7.2	Enumeration Icu_ActivationType.....	33
3.7.3	Enumeration Icu_InputStateType.....	33
3.7.4	Enumeration Icu_MeasurementModeType.....	33
3.7.5	Enumeration Icu_ModeType.....	33
3.7.6	Enumeration Icu_SignalMeasurementPropertyType.....	34
3.7.7	Enumeration Icu_TimestampBufferType.....	34
3.7.8	Enumeration Icu_WakeupCapableType.....	34
3.8	Typedef Definitions.....	35
3.8.1	Typedef Icu_ChannelType.....	35
3.8.2	Typedef Icu_MeasurementSubModeType.....	35
3.8.3	Typedef Icu_ParamType.....	35
3.9	Define Definitions.....	35
3.9.1	Define ICU_DEINIT_ID.....	35

Section Number	Title	Page
3.9.2	Define ICU_DISABLEEDGECOUNT_ID.....	36
3.9.3	Define ICU_DISABLENOTIFICATION_ID.....	36
3.9.4	Define ICU_DISABLEWAKEUP_ID.....	36
3.9.5	Define ICU_ENABLEEDGECOUNT_ID.....	36
3.9.6	Define ICU_ENABLENOTIFICATION_ID.....	36
3.9.7	Define ICU_ENABLEWAKEUP_ID.....	37
3.9.8	Define ICU_GETDUTYCYCLEVALUES_ID.....	37
3.9.9	Define ICU_GETEDGENUMBERS_ID.....	37
3.9.10	Define ICU_GETINPUTSTATE_ID.....	37
3.9.11	Define ICU_GETTIMEELAPSED_ID.....	37
3.9.12	Define ICU_GETTIMESTAMPINDEX_ID.....	38
3.9.13	Define ICU_GETVERSIONINFO_ID.....	38
3.9.14	Define ICU_INIT_ID.....	38
3.9.15	Define ICU_RESETEGECOUNT_ID.....	38
3.9.16	Define ICU_SET_CLOCK_MODE_ID.....	38
3.9.17	Define ICU_SETACTIVATIONCONDITION_ID.....	39
3.9.18	Define ICU_SETMODE_ID.....	39
3.9.19	Define ICU_STARTSIGNALMEASUREMENT_ID.....	39
3.9.20	Define ICU_STARTTIMESTAMP_ID.....	39
3.9.21	Define ICU_STOPSIGNALMEASUREMENT_ID.....	39
3.9.22	Define ICU_STOPTIMESTAMP_ID.....	40
3.9.23	Define ICU_E_ALREADY_INITIALIZED.....	40
3.9.24	Define ICU_E_BUSY_OPERATION.....	40
3.9.25	Define ICU_E_EDGECOUNTING_OVERFLOW.....	40
3.9.26	Define ICU_E_MEASUREMENT_OVERFLOW.....	40
3.9.27	Define ICU_E_NOT_STARTED.....	40
3.9.28	Define ICU_E_PARAM_ACTIVATION.....	41
3.9.29	Define ICU_E_PARAM_BUFFER_PTR.....	41
3.9.30	Define ICU_E_PARAM_BUFFER_SIZE.....	41

Section Number	Title	Page
3.9.31	Define ICU_E_PARAM_CHANNEL.....	41
3.9.32	Define ICU_E_PARAM_CLOCK_MODE.....	41
3.9.33	Define ICU_E_PARAM_CONFIG.....	41
3.9.34	Define ICU_E_PARAM_MODE.....	41
3.9.35	Define ICU_E_TIMESTAMP_OVERFLOW.....	42
3.9.36	Define ICU_E_UNINIT.....	42
3.10	Symbolic Names DISCLAIMER.....	42
3.11	Configuration Parameters.....	42
3.11.1	Plugin interface.....	43
3.11.2	Pre-Compile Parameters.....	46
3.11.2.1	IcuMaxChannel.....	47
3.11.2.2	IcuIndex.....	47
3.11.2.3	IcuDevErrorDetect.....	48
3.11.2.4	IcuReportWakeupSource.....	48
3.11.2.5	IcuEnableDualClockMode.....	48
3.11.2.6	IcuDeInitApi.....	49
3.11.2.7	IcuDisableWakeupApi.....	49
3.11.2.8	IcuEdgeCountApi.....	49
3.11.2.9	IcuEnableWakeupApi.....	50
3.11.2.10	IcuGetDutyCycleValuesApi.....	50
3.11.2.11	IcuGetInputStateApi.....	50
3.11.2.12	IcuGetTimeElapsedApi.....	51
3.11.2.13	IcuGetVersionInfoApi.....	51
3.11.2.14	IcuSetModeApi.....	51
3.11.2.15	IcuTimestampApi.....	52
3.11.2.16	IcuSignalMeasurementApi.....	52
3.11.2.17	IcuChannelId.....	52
3.11.2.18	IcuHwChannel.....	53
3.11.2.19	icuoverflownotificationapi.....	53

Section Number	Title	Page
3.11.3	Link Time parameters.....	53
3.11.4	Post - Build Parameters.....	54
3.11.4.1	Icu_ParamType.....	55
3.11.4.2	IcuEmiosFreeze.....	57
3.11.4.3	IcuEmiosPrescaler.....	57
3.11.4.4	IcuEmiosPrescaler_Alternate.....	58
3.11.4.5	IcuEmiosDigitalFilter.....	59
3.11.4.6	IcuEmiosBusSelect.....	60
3.11.4.7	IcuDefaultStartEdge.....	60
3.11.4.8	IcuMeasurementMode.....	61
3.11.4.9	IcuUserModeForDutycycle.....	61
3.11.4.10	IcuWakeupCapability.....	62
3.11.4.11	IcuSignalNotification.....	63
3.11.4.12	IcuSignalMeasurementProperty.....	64
3.11.4.13	IcuTimestampMeasurementProperty.....	64
3.11.4.14	IcuTimestampNotification.....	65
3.11.4.15	IcuChannelWakeupInfo.....	66
3.11.4.16	IcuOverflowNotification.....	66





# Chapter 1

## Revision History

**Table 1-1. Revision History**

Revision	Date	Author	Description
1.0	27.01.2011	Chandrakanth.P	Initial Version
2.0	27.11.2011	Syed Hussaini	Updated for Monaco RTM2.0.0



# Chapter 2

## Introduction

This User Manual describes Freescale Semiconductor AUTOSAR microcontroller abstraction layer (MCAL) Input Capture Unit (ICU) for MPC5634M microcontroller.

AUTOSAR ICU driver configuration parameters and deviations from the specification are described in Icu Driver chapter of this document. AUTOSAR ICU driver requirements and APIs are described in the AUTOSAR ICU driver software specification document.

### 2.1 Supported Derivatives

The software described in this document is intended to be used with the following microcontroller devices of Freescale Semiconductor:

**Table 2-1. MPC5634M Supported Derivatives**

Freescale Semiconductor	mpc5634m_bga208, mpc5634m_qfp144, mpc5634m_qfp176
-------------------------	---

All of the above microcontroller devices are collectively named as **MPC5634M**.

### 2.2 Overview

**AUTOSAR (AUTomotive Open System ARchitecture)** is an industry partnership working to establish standards for software interfaces and software modules for automobile electronic control systems.

#### AUTOSAR

- paves the way for innovative electronic systems that further improve performance, safety and environmental friendliness.

- is a strong global partnership that creates one common standard: "Cooperate on standards, compete on implementation".
- is a key enabling technology to manage the growing electrics/electronics complexity. It aims to be prepared for the upcoming technologies and to improve cost-efficiency without making any compromise with respect to quality.
- facilitates the exchange and update of software and hardware over the service life of the vehicle.

## 2.3 About this Manual

This Technical Reference employs the following typographical conventions:

**Boldface** type: Bold is used for important terms, notes and warnings.

*Italic* font: Italic typeface is used for code snippets in the text. Note that C language modifiers such "const" or "volatile" are sometimes omitted to improve readability of the presented code.

## 2.4 Acronyms and Definitions

**Table 2-2. Acronyms and Definitions**

Abbreviation and Definitions	Description
BSW	Basic Software
DEM	Diagnostic Event Manager
DET	Development Error Tracer
ECU	Electronic Control Unit
ICU	Input Capture Unit
ISR	interrupt Service Routine
OS	Operating System
RAM	Random Access Memory
ROM	Read-only Memory
MCU	Microcontroller Unit
GUI	Graphical User Interface
EcuM	ECU state Manager
API	Application Programming Interface
PB Variant	Post Build Variant
PC Variant	Pre Compile Variant

## 2.5 Reference List

**Table 2-3. Reference List**

#	Title	Version
1	AUTOSAR 3.0ICU Driver Software Specification Document.	V2.2.0 R3.0 Rev 0001
2	MPC5634M Reference Manual	Rev. 6, 4 October 2011



## Chapter 3 Driver

### 3.1 Requirements

Requirements for this driver are detailed in the AUTOSAR 3.0ICUDriver Software Specification document (See Table [Reference List](#)).

### 3.2 Driver Design Summary

The ICU Driver controls the input capture of the micro controller. It provides the following features:

- Period time measurement
- Edge detection and notification
- Edge counting (with or without hardware gating)
- Edge time stamping

For signal edge detection, the edge detector of a capture compare unit or the interrupt controller for external events is used.

For signal measuring a capture timer and at least one capture register is needed.

### 3.3 Hardware channel availability

The eMIOS module of MPC5634M supports all above mentioned features of ICU module.

**Table 3-1. ICU Hardware channels availability for MPC5634Mfamily**

Device	Total eMIOS channels	Total External interrupt channels
MPC5634M	24 ch, 16-bit	16 ch

### 3.4 Additional Requirements and Deviations

Deviations from the AUTOSAR ICU Driver software specification are listed in table **Deviations Status Column Description**.

**Table 3-2. Deviations Status Column Description**

Term	Definition
N/A	Not available
N/T	Not testable
N/S	Out of scope
N/I	Not implemented
N/F	Not fully implemented

Below table identifies the AUTOSAR requirements that are not fully implemented, implemented differently, or out of scope for the ICU driver.

**Table 3-3. ICU Deviations Table**

Requirement	Status	Description	Notes
ICU003	N/I	Production errors shall be reported to the Diagnostic Event Manager (DEM).	No Production Error

*Table continues on the next page...*



**Table 3-3. ICU Deviations Table (continued)**

Requirement	Status	Description	Notes
ICU039	N/F	Configuration of Signal Measurement - This container contains the configuration (parameters) in case the measurement mode is "ICU_MODE_SIGNAL_MEASUREMENT" The definition for each Channel shall contain: Common parameters § Wakeup capability (true / false) § Default Start Edge § Hardware Specific Settings per channel § Measurement Mode - Signal Edge Detection / Notification - Signal Measurement - Timestamp - Edge Counter Specific parameters § If measurement mode is "signal edge detection" the notification function for signal notification shall be configurable § If measurement mode is "signal measurement" the property that could be measured shall be configurable. The values shall be: - High Time - Low Time - Period Time - Duty Cycle Values (High Time and Period Time) § If measurement mode is "timestamp measurement", buffer handling shall be configurable. The values shall be: - Circular buffer handling - Linear buffer handling Also the notification function for notifying the number of requested timestamps shall be configurable § If measurement mode is "edge counter", the counting mode (activation edge) shall be configurable. The values shall be: - Rising Edge - Falling Edge - Both edges § If the channel is configured as wakeup capable, - the callout function for validation of wakeup reason shall be configurable - The value transmitted to the EcuM shall be configurable § Assigned capture register(s) (can also be none for channels which provide only edge detection like an external interrupt) Assigned capture timer (can also be none for channels which provide only edge detection like an external interrupt)	For memory space saving capture register and capture timer were omitted, indexed access is used. Capture registers and capture timer are not enough for this architecture, it would require also the control register and the status register. Because registers in memory are very well organized, the access to these registers was done by macros that access memory with offset depending the channel used.
ICU052	N/S	Icu_Init - If the register can affect several hardware modules and if it is an I/O register it shall be initialized by the PORT driver.	Not an ICU driver requirement
ICU053	N/S	Icu_Init - If the register can affect several hardware modules and if it is not an I/O register it shall be initialized by the MCU driver.	Not an ICU driver requirement
ICU113	N/I	The detection of production code errors cannot be switched off. Specification of ICU Driver	No Production Error

*Table continues on the next page...*

**Table 3-3. ICU Deviations Table (continued)**

Requirement	Status	Description	Notes
ICU116	N/I	The module shall include the Dem.h file. By this inclusion the API's to report errors as well as the required Event Id symbols are included. This specification defines the name of the Event Id symbols which are provided by XML to the DEM configuration tool. The DEM configuration tool assigns ECU dependent values to the Event Id symbols and publishes the symbols in Dem_IntErrId.h.	No Production Error
ICU117	N/I	Values for production code event ID's are assigned externally by the configuration of the DEM. They are published in the file Dem_IntErrId.h and included via Dem.h.	No Production Error
ICU128	N/S	One-time writable registers that require initialization directly after reset shall be initialized by the startup code.	Not an ICU driver requirement
ICU129	N/S	All other registers shall be initialized by the startup code.	Not an ICU driver requirement
ICU131	N/I	The ICU driver shall describe which other modules (in which versions) are required. This description shall be done by the implementer.	Port Driver Mcu Driver (FMPLL)

## 3.5 Function Definitions

APIs of all functions supported by the driver are as per AUTOSAR ICU Driver software specification Version 3.0.

### 3.5.1 Function Icu\_Init

This function initializes the driver.

**Prototype:** `void Icu_Init(const Icu_ConfigType *ConfigPtr);`

**Table 3-4. Icu\_Init Arguments**

Type	Name	Direction	Description
const Icu_ConfigType *	ConfigPtr	input	Pointer to a selected configuration structure.

This service is a non reentrant function used for driver initialization. The Initialization function shall initialize all relevant registers of the configured hardware with the values of the structure referenced by the parameter ConfigPtr. If the hardware allows for only

one usage of the register, the driver module implementing that functionality is responsible for initializing the register. The initialization function of this module shall always have a pointer as a parameter, even though for Variant PC no configuration set shall be given. Instead a NULL pointer shall be passed to the initialization function. The Icu module environment shall not call Icu\_Init during a running operation (e. g. timestamp measurement or edge counting).

**Remarks:**

- Covers ICU002, ICU111, ICU220, ICU023, ICU054, ICU060
- Implements DICU20100, DICU01015, DICU10001

### 3.5.2 Function Icu\_DeInit

This function de-initializes the ICU module.

**Prototype:** `void Icu_DeInit(void);`

This service is a Non reentrant function used for ICU De-Initialization After the call of this service, the state of the peripherals used by configuration shall be the same as after power on reset. Values of registers which are not writable are excluded. This service shall disable all used interrupts and notifications. The Icu module environment shall not call Icu\_DeInit during a running operation (e. g. timestamp measurement or edge counting)

**pre.:** Icu\_Init must be called before.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU091, ICU036
- Implements DICU01002, DICU10002

### 3.5.3 Function Icu\_SetMode

This function sets the ICU mode.

**Prototype:** `void Icu_SetMode(Icu_ModeType Mode);`

**Table 3-5. Icu\_SetMode Arguments**

Type	Name	Direction	Description
Icu_ModeType	Mode	input	Specifies the operation mode

This service is a non reentrant function used for ICU mode selection. This service shall set the operation mode to the given mode parameter. This service can be called during running operations. If so, an ongoing operation that generates interrupts on a wakeup

capable channel like e.g. time stamping or edge counting might lead to the ICU module not being able to properly enter sleep mode. This is then a system or ECU configuration issue not a problem of this specification.

**pre::** Icu\_Init must be called before.

**Remarks:**

- Covers ICU002, ICU111, ICU022, ICU048, ICU095, ICU125, ICU011, ICU012
- Implements DICU01020, DICU10003

### 3.5.4 Function Icu\_SetClockMode

This function changes the channel prescaler.

**Prototype:** void Icu\_SetClockMode(Icu\_SelectPrescalerType Prescaler);

**Table 3-6. Icu\_SetClockMode Arguments**

Type	Name	Direction	Description
Icu_SelectPrescalerType	Prescaler	input	- Prescaler type ( Normal or Alternate )

This function sets all channels prescalers based on the input mode.

**pre::** Icu\_Init must be called before.

### 3.5.5 Function Icu\_DisableWakeup

This function disables the wakeup capability of a single ICU channel.

**Prototype:** void Icu\_DisableWakeup(Icu\_ChannelType Channel);

**Table 3-7. Icu\_DisableWakeup Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel

This service is reentrant function and shall disable the wakeup capability of a single ICU channel. This service is only feasible for ICU channels configured statically as wakeup capable true. The function Icu\_DisableWakeup shall be pre compile time configurable On/Off by the configuration parameter IcuDisableWakeupApi.

**pre::** Icu\_Init must be called before.

**Remarks:**

- Covers ICU002, ICU111, ICU022, ICU048, ICU024, ICU059
- Implements DICU01005, DICU10004

### 3.5.6 Function Icu\_EnableWakeup

This function (re-)enables the wakeup capability of the given ICU channel.

**Prototype:** void Icu\_EnableWakeup(Icu\_ChannelType Channel);

**Table 3-8. Icu\_EnableWakeup Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel

The function is reentrant and re-enable the wake-up capability of a single ICU channel.

**pre::** Icu\_Init must be called before. The channel must be configured as wakeup capable.

**Remarks:**

- Covers ICU002, ICU111, ICU022, ICU048, ICU155, ICU156
- Implements DICU01008, DICU10005

### 3.5.7 Function Icu\_SetActivationCondition

This function sets the activation-edge for the given channel.

**Prototype:** void Icu\_SetActivationCondition(Icu\_ChannelType Channel, Icu\_ActivationType Activation);

**Table 3-9. Icu\_SetActivationCondition Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel
Icu_ActivationType	Activation	input	Type of activation.

This service is reentrant and shall set the activation-edge according to Activation parameter for the given channel.

This service shall support channels which are configured

for the following Icu\_MeasurementMode:

ICU\_MODE\_SIGNAL\_EDGE\_DETECT

ICU\_MODE\_TIMESTAMP

ICU\_MODE\_EDGE\_COUNTER

**pre::** Icu\_Init must be called before. The channel must be properly configured ICU\_MODE\_SIGNAL\_EDGE\_DETECT, ICU\_MODE\_TIMESTAMP, ICU\_MODE\_EDGE\_COUNTER.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU159, ICU043
- Implements DICU01019, DICU10006

### 3.5.8 Function Icu\_DisableNotification

This function disables the notification of a channel.

**Prototype:** void Icu\_DisableNotification(Icu\_ChannelType Channel);

**Table 3-10. Icu\_DisableNotification Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel

This function is reentrant and disables the notification of a channel.

**pre::** Icu\_Init must be called before.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU160
- Implements DICU01004, DICU10007

### 3.5.9 Function Icu\_EnableNotification

This function enables the notification on the given channel.

**Prototype:** void Icu\_EnableNotification(Icu\_ChannelType Channel);

**Table 3-11. Icu\_EnableNotification Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel

This function is reentrant and enables the notification on the given channel.

**pre::** Icu\_Init must be called before.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU161
- Implements DICU01007, DICU10008

**3.5.10 Function Icu\_GetInputState**

This function returns the status of the ICU input.

**Prototype:** `Icu_InputStateType Icu_GetInputState(Icu_ChannelType Channel);`

**Table 3-12. Icu\_GetInputState Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel

This service is reentrant shall return the status of the ICU input.

Only channels which are configured for the following Icu\_MeasurementMode shall be supported:

ICU\_MODE\_SIGNAL\_EDGE\_DETECT,

ICU\_MODE\_SIGNAL\_MEASUREMENT.

**Return:** Icu\_InputStateType - ICU\_ACTIVE: An activation edge has been detected, ICU\_IDLE: No activation edge has been detected since the last call of Icu\_GetInputState() Or Icu\_Init().

**pre.:** Icu\_Init must be called before.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU162
- Implements DICU01011, DICU10009

**3.5.11 Function Icu\_StartTimestamp**

This function starts the capturing of timer values on the edges.

**Prototype:** `void Icu_StartTimestamp(Icu_ChannelType Channel, Icu_ValueType *BufferPtr, uint16 BufferSize, uint16 NotifyInterval);`

**Table 3-13. Icu\_StartTimestamp Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel
Icu_ValueType *	BufferPtr	input	Pointer to the buffer-array where the timestamp values shall be placed.
uint16	BufferSize	input	Size of the external buffer (number of entries)
uint16	NotifyInterval	input	Notification interval (number of events).

This function is reentrant and starts the capturing of timer values on the edges activated by the service `Icu_SetActivationCondition()` to an external buffer.

**pre::** `Icu_Init` must be called before.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU163, ICU120, ICU108
- Implements DICU01022, DICU10010

### 3.5.12 Function Icu\_StopTimestamp

This function stops the timestamp measurement of the given channel.

**Prototype:** `void Icu_StopTimestamp(Icu_ChannelType Channel);`

**Table 3-14. Icu\_StopTimestamp Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel

This function is reentrant and stops the timestamp measurement of the given channel.

**pre::** `Icu_Init` must be called before.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU164, ICU166
- Implements DICU01024, DICU10011

### 3.5.13 Function Icu\_GetTimestampIndex

This function reads the timestamp index of the given channel.

**Prototype:** `Icu_IndexType Icu_GetTimestampIndex(Icu_ChannelType Channel);`



**Table 3-15. Icu\_GetTimestampIndex Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel

This function is reentrant and reads the timestamp index of the given channel, which is next to be written.

**Return:** Icu\_IndexType - Timestamp index of the given channel

**pre::** Icu\_Init must be called before. Icu\_StartTimestamp must be called before.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU169, ICU107, ICU004
- Implements DICU01013, DICU10012

### 3.5.14 Function Icu\_ResetEdgeCount

This function resets the value of the counted edges to zero.

**Prototype:** void Icu\_ResetEdgeCount(Icu\_ChannelType Channel);

**Table 3-16. Icu\_ResetEdgeCount Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel.

This function is reentrant and resets the value of the counted edges to zero.

**pre::** Icu\_Init must be called before.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU171
- Implements DICU01018, DICU10013

### 3.5.15 Function Icu\_EnableEdgeCount

This function enables the counting of edges of the given channel.

**Prototype:** void Icu\_EnableEdgeCount(Icu\_ChannelType Channel);

**Table 3-17. Icu\_EnableEdgeCount Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel

This service is reentrant and shall enable the counting of edges of the given channel.

Note: This service does not do the real counting itself. This is done by the hardware (capture unit). Only the configured edges shall be counted (rising edge / falling edge / both edges).

Configuration of the edge is done in `Icu_Init` or `Icu_SetActivationCondition`. The configured edge can be changed during runtime using

`Icu_SetActivationCondition`. Interrupts are not required for edge counting. If interrupts are enabled, the interrupt service routine will set the overflow flag if more than 0xFFFFF edges are measured.

**pre::** `Icu_Init` must be called before. The given channel must be configured in Measurement Mode Edge Counter.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU172
- Implements DICU01006, DICU10014

### 3.5.16 Function `Icu_DisableEdgeCount`

This function disables the counting of edges of the given channel.

**Prototype:** `void Icu_DisableEdgeCount(Icu_ChannelType Channel);`

**Table 3-18. `Icu_DisableEdgeCount` Arguments**

Type	Name	Direction	Description
<code>Icu_ChannelType</code>	Channel	input	Numeric identifier of the ICU channel

This function is reentrant and disables the counting of edges of the given channel.

**pre::** `Icu_Init` must be called before. The given channel must be configured in Measurement Mode Edge Counter.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU173
- Implements DICU01003, DICU10015

### 3.5.17 Function `Icu_GetEdgeNumbers`

This function reads the number of counted edges.

**Prototype:** `Icu_EdgeNumberType Icu_GetEdgeNumbers(Icu_ChannelType Channel);`

**Table 3-19. Icu\_GetEdgeNumbers Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel

This function is reentrant reads the number of counted edges after the last call of `Icu_ResetEdgeCount()`.

**Return:** Icu\_EdgeNumberType - Number of the counted edges.

**pre::** Icu\_Init must be called before. The given channel must be configured in Measurement Mode Edge Counter.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU107, ICU174, ICU175, ICU004
- Implements DICU01010, DICU10016

### 3.5.18 Function Icu\_StartSignalMeasurement

This function starts the measurement of signals.

**Prototype:** `void Icu_StartSignalMeasurement(Icu_ChannelType Channel);`

**Table 3-20. Icu\_StartSignalMeasurement Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel

This service is reentrant and starts the measurement of signals beginning with the configured default start edge which occurs first after the call of this service. This service shall only be available in Measurement Mode `ICU_MODE_SIGNAL_MEASUREMENT`. This service shall reset the state for the given channel to `ICU_IDLE`.

**pre::** Icu\_Init must be called before. The given channel must be configured in Measurement Mode Signal Measurement.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU176
- Implements DICU01021, DICU10017

### 3.5.19 Function Icu\_StopSignalMeasurement

This function stops the measurement of signals of the given channel.

**Prototype:** `void Icu_StopSignalMeasurement(Icu_ChannelType Channel);`

**Table 3-21. Icu\_StopSignalMeasurement Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel

This function is reentrant and stops the measurement of signals of the given channel.

**pre::** Icu\_Init must be called before. The given channel must be configured in Measurement Mode Signal Measurement.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU177
- Implements DICU01023, DICU10018

### 3.5.20 Function Icu\_GetTimeElapsed

This function reads the elapsed Signal Low/High/Period Time for the given channel.

**Prototype:** `Icu_ValueType Icu_GetTimeElapsed(Icu_ChannelType Channel);`

**Table 3-22. Icu\_GetTimeElapsed Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel

This service is reentrant and reads the elapsed Signal Low Time for the given channel that is configured in Measurement Mode Signal Measurement, Signal Low Time. The elapsed time is measured between a falling edge and the consecutive rising edge of the channel. This service reads the elapsed Signal High Time for the given channel that is configured in Measurement Mode Signal Measurement, Signal High Time. The elapsed time is measured between a rising edge and the consecutive falling edge of the channel. This service reads the elapsed Signal Period Time for the given channel that is configured in Measurement Mode Signal Measurement, Signal Period Time. The elapsed time is measured between consecutive rising (or falling) edges of the channel. The period start edge is configurable.

**Return:** Icu\_ValueType - The elapsed Signal Low Time for the given channel

**pre::** Icu\_Init must be called before. The given channel must be configured in Measurement Mode Signal Measurement.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU107, ICU178, ICU004, ICU179, ICU136
- Implements DICU01012, DICU10019

**3.5.21 Function Icu\_GetDutyCycleValues**

This function reads the coherent active time and period time for the given ICU Channel.

**Prototype:** void Icu\_GetDutyCycleValues(Icu\_ChannelType Channel, Icu\_DutyCycleType \*DutyCycleValues);

**Table 3-23. Icu\_GetDutyCycleValues Arguments**

Type	Name	Direction	Description
Icu_ChannelType	Channel	input	Numeric identifier of the ICU channel
Icu_DutyCycleType *	DutyCycleValues	output	Pointer to a buffer where the results (high time and period time) shall be placed.

The function is reentrant and reads the coherent active time and period time for the given ICU Channel, if it is configured in Measurement Mode Signal Measurement, Duty Cycle Values.

**pre::** Icu\_Init must be called before. The given channel must be configured in Measurement Mode Signal Measurement, Duty Cycle Values.

**Remarks:**

- Covers ICU002, ICU111, ICU112, ICU022, ICU048, ICU180, ICU107, ICU004, ICu181, ICU137
- Implements DICU01009, DICU10020

**3.5.22 Function Icu\_GetVersionInfo**

This service returns the version information of this module.

**Prototype:** void Icu\_GetVersionInfo(Std\_VersionInfoType \*versioninfo);

**Table 3-24. Icu\_GetVersionInfo Arguments**

Type	Name	Direction	Description
Std_VersionInfoType *	versioninfo	output	Pointer to location to store version info

This service is Non reentrant and returns the version information of this module.

The version information includes:

- Module Id
- Vendor Id
- Vendor specific version numbers

If source code for caller and callee of this function is available this function should be realized as a macro. The macro should be defined in the modules header file.

**Remarks:**

- Covers ICU005
- Implements DICU01014

## **3.6 Structure Definitions**

Data structures supported by the driver are as per AUTOSAR ICU Driver software specification Version 3.0.

### **3.6.1 Structure Icu\_ConfigType**

This type contains initialization data. The notification functions shall be configurable as function pointers within the initialization data structure (`Icu_ConfigType`). This type of the external data structure shall contain the initialization data for the ICU driver. It shall contain:

- Wakeup Module Info (in case the wakeup-capability is true)
- ICU dependent properties for used HW units
- Clock source with optional prescaler (if provided by HW)

#### **Declaration**

```
typedef struct
{
    const Icu_ChannelConfigType * Icu_ChannelConfigPtr,
    const Icu_ChannelType * Icu_ChannelId,
    const Icu_ChannelType * Icu_ChannelIndex,
    const Icu_ChannelType * Icu_HWMap,
    const Icu_ChannelType * Icu_HWWKMap,
    const Icu_ChannelType Icu_MaxChannels
} Icu_ConfigType;
```

**Table 3-25. Structure Icu\_ConfigType member description**

Member	Description
Icu_ChannelConfigPtr	Pointer to Icu channel configuration.
Icu_ChannelId	Array for mapping the Icu channels to hardware channels.
Icu_ChannelIndex	This index relates the Icu Channel number with the respective global variable, depending on the measurement mode. Each kind of measurement mode has an array(s) in the ICU driver.
Icu_HWMap	This index relates the Hardware channels with the respective ICU channel.
Icu_HWWKMap	This index relates the Wakeup pins with the respective ICU channel.
Icu_MaxChannels	The number of configured channels.

**Remarks:**

- Covers ICU038, ICU039, ICU190
- Implements DICU50200

**3.6.2 Structure Icu\_ChannelConfigType**

Structure that contains ICU channel configuration. It contains the information like Icu Channel Mode, Channel Notification function, Overflow Notification function.

**Declaration**

```
typedef struct
{
    Icu_MeasurementModeType Icu_Channel_Mode,
    Icu_NotifyType Icu_Channel_Notification,
    Icu_NotifyType Icu_Channel_OverFlowNotification,
    Icu_MeasurementSubModeType Icu_Channel_Property,
    Icu_WakeupValue Icu_Channel_WakeupValue,
    Icu_ParamType Icu_ParamValue
} Icu_ChannelConfigType;
```

**Table 3-26. Structure Icu\_ChannelConfigType member description**

Member	Description
Icu_Channel_Mode	Icu Measurement mode type i.e EDGE_DETECT, TIME_STAMP, SIGNAL_MEASUREMENT or EDGE_COUNTER.
Icu_Channel_Notification	Icu Channel Notification function for TIME_STAMP or EDGE_COUNTER mode.
Icu_Channel_OverFlowNotification	Icu Custom notification function. Icu Channel Overflow Notification function
Icu_Channel_Property	Icu Channel Property type i.e CIRCULAR_BUFFER or LINEAR_BUFFER for TIME_STAMP, DUTY_CYCLE, HIGH_TIME, LOW_TIME or PERIOD_TIME for SIGNAL_MEASUREMENT and RISING_EDGE, FALLING_EDGE or BOTH_EDGES for EDGE_COUNTER.

*Table continues on the next page...*

**Table 3-26. Structure Icu\_ChannelConfigType member description (continued)**

Member	Description
Icu_Channel_WakeupValue	EcuM wakeup source Id.
Icu_ParamValue	Configuration parameters of IP registers.

**Remarks:**

- Implements DICU50202

**3.6.3 Structure Icu\_DutyCycleType**

Structure that contains ICU Duty cycle parameters. It contains contain the values, needed for calculating duty cycles i.e Period time value and Active time value.

**Declaration**

```
typedef struct
{
    Icu_ValueType ActiveTime,
    Icu_ValueType PeriodTime
} Icu_DutyCycleType;
```

**Table 3-27. Structure Icu\_DutyCycleType member description**

Member	Description
ActiveTime	Low or High time value.
PeriodTime	Period time value.

**3.7 Enum Definitions**

Data Enums supported by the driver are as per AUTOSAR ICU Driver software specification Version 3.0.

**3.7.1 Enumeration Icu\_SelectPrescalerType**

Enumeration of available prescalers.

**Table 3-28. Enumeration Icu\_SelectPrescalerType Values**

Value	Description
ICU_NORMAL = 0x0U	Default channel prescaler option
ICU_ALTERNATE = 0x1U	Alternative prescaler to be used depending on user application ( e.g. low power modes )



### 3.7.2 Enumeration Icu\_ActivationType

Definition of the type of activation of an ICU channel.

**Table 3-29. Enumeration Icu\_ActivationType Values**

Value	Description
ICU_FALLING_EDGE = 0x0U	ICU_FALLING_EDGE = An appropriate action shall be executed when a falling edge occurs on the ICU input signal.
ICU_RISING_EDGE = 0x1U	ICU_RISING_EDGE = An appropriate action shall be executed when a rising edge occurs on the ICU input signal.
ICU_BOTH_EDGES = 0x2U	ICU_BOTH_EDGES = An appropriate action shall be executed when either a rising or falling edge occur on the ICU input signal.

### 3.7.3 Enumeration Icu\_InputStateType

Input state of an ICU channel.

**Table 3-30. Enumeration Icu\_InputStateType Values**

Value	Description
ICU_ACTIVE = 0U	ICU_ACTIVE = An activation edge has been detected
ICU_IDLE	ICU_IDLE = No activation edge has been detected since the last call of Icu_GetInputState() or Icu_Init().

### 3.7.4 Enumeration Icu\_MeasurementModeType

Definition of the measurement mode type.

**Table 3-31. Enumeration Icu\_MeasurementModeType Values**

Value	Description
ICU_MODE_SIGNAL_EDGE_DETECT = 0U	ICU_MODE_SIGNAL_EDGE_DETECT = Mode for detecting edges
ICU_MODE_SIGNAL_MEASUREMENT	ICU_MODE_SIGNAL_MEASUREMENT = Mode for measuring different times between various configurable edges
ICU_MODE_TIMESTAMP	ICU_MODE_TIMESTAMP = Mode for capturing timer values on configurable edges
ICU_MODE_EDGE_COUNTER	ICU_MODE_EDGE_COUNTER = Mode for counting edges on configurable edges

### 3.7.5 Enumeration Icu\_ModeType

Allow enabling / disabling of all interrupts which are not required for the ECU wakeup.

**Table 3-32. Enumeration Icu\_ModeType Values**

Value	Description
ICU_MODE_NORMAL = 0U	ICU_MODE_NORMAL = Normal operation, all used interrupts are enabled according to the notification requests.
ICU_MODE_SLEEP	ICU_MODE_SLEEP = Reduced power operation. In sleep mode only those notifications are available which are configured as wakeup capable.

### 3.7.6 Enumeration Icu\_SignalMeasurementPropertyType

Definition of the measurement property type.

**Table 3-33. Enumeration Icu\_SignalMeasurementPropertyType Values**

Value	Description
ICU_LOW_TIME = 0U	ICU_LOW_TIME = The channel is configured for reading the elapsed Signal Low Time
ICU_HIGH_TIME	ICU_HIGH_TIME = The channel is configured for reading the elapsed Signal High Time
ICU_PERIOD_TIME	ICU_PERIOD_TIME = The channel is configured for reading the elapsed Signal Period Time
ICU_DUTY_CYCLE	ICU_DUTY_CYCLE = The channel is configured to read values which are needed for calculating the duty cycle (coherent Active and Period Time).

### 3.7.7 Enumeration Icu\_TimestampBufferType

Definition of the timestamp measurement property type.

**Table 3-34. Enumeration Icu\_TimestampBufferType Values**

Value	Description
ICU_LINEAR_BUFFER = 0U	ICU_LINEAR_BUFFER = The buffer will just be filled once
ICU_CIRCULAR_BUFFER	ICU_CIRCULAR_BUFFER = After reaching the end of the buffer, the driver restarts at the beginning of the buffer

### 3.7.8 Enumeration Icu\_WakeupCapableType

Definition of the type of wake up capability of an ICU channel.

**Table 3-35. Enumeration Icu\_WakeupCapableType Values**

Value	Description
ICU_WAKEUP_NOTCAPABLE = 0x0U	ICU_WAKEUP_NOTCAPABLE = Channel is not wakeup capable
ICU_WAKEUP_CAPABLE = 0x1U	ICU_WAKEUP_CAPABLE = Channel is wakeup capable.

## 3.8 Typedef Definitions

Data Typedefs supported by the driver are as per AUTOSAR ICU Driver software specification Version 3.0.

### 3.8.1 Typedef Icu\_ChannelType

Type Definitions.

**Type:** uint8

This gives the numeric ID (hardware channel number) of an ICU channel

### 3.8.2 Typedef Icu\_MeasurementSubModeType

**Type:** uint8

Type for saving the ICU measurement submode type

### 3.8.3 Typedef Icu\_ParamType

**Type:** uint32

Icu\_ParamType is defined as a uint32. The Icu\_ParamValue contains combined bit fields for initialization options, for different registers.

## 3.9 Define Definitions

### 3.9.1 Define ICU\_DEINIT\_ID

API service ID for Icu\_DeInit function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_DEINIT_ID 0x01U`

### 3.9.2 Define ICU\_DISABLEEDGECOUNT\_ID

API service ID for Icu\_DisableEdgeCount function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_DISABLEEDGECOUNT_ID 0x0EU`

### 3.9.3 Define ICU\_DISABLENOTIFICATION\_ID

API service ID for Icu\_DisableNotification function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_DISABLENOTIFICATION_ID 0x06U`

### 3.9.4 Define ICU\_DISABLEWAKEUP\_ID

API service ID for Icu\_DisableWakeup function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_DISABLEWAKEUP_ID 0x03U`

### 3.9.5 Define ICU\_ENABLEEDGECOUNT\_ID

API service ID for Icu\_EnableEdgeCount function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_ENABLEEDGECOUNT_ID 0x0DU`

### 3.9.6 Define ICU\_ENABLENOTIFICATION\_ID

API service ID for Icu\_EnableNotification function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_ENABLENOTIFICATION_ID 0x07U`

### 3.9.7 Define ICU\_ENABLEWAKEUP\_ID

API service ID for Icu\_EnableWakeup function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_ENABLEWAKEUP_ID 0x04U`

### 3.9.8 Define ICU\_GETDUTYCYCLEVALUES\_ID

API service ID for Icu\_GetDutyCycleValues function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_GETDUTYCYCLEVALUES_ID 0x11U`

### 3.9.9 Define ICU\_GETEDGENUMBERS\_ID

API service ID for Icu\_GetEdgeNumbers function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_GETEDGENUMBERS_ID 0x0FU`

### 3.9.10 Define ICU\_GETINPUTSTATE\_ID

API service ID for Icu\_GetInputState function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_GETINPUTSTATE_ID 0x08U`

### 3.9.11 Define ICU\_GETTIMEELAPSED\_ID

API service ID for Icu\_GetTimeElapsed function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_GETTIMEELAPSED_ID 0x10U`

### 3.9.12 Define ICU\_GETTIMESTAMPINDEX\_ID

API service ID for Icu\_GetTimestampIndex function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_GETTIMESTAMPINDEX_ID 0x0BU`

### 3.9.13 Define ICU\_GETVERSIONINFO\_ID

API service ID for Icu\_GetVersionInfo function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_GETVERSIONINFO_ID 0x12U`

### 3.9.14 Define ICU\_INIT\_ID

API service ID for Icu\_Init function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_INIT_ID 0x00U`

### 3.9.15 Define ICU\_RESETEDEGECOUNT\_ID

API service ID for Icu\_ResetEdgeCount function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_RESETEDEGECOUNT_ID 0x0CU`

### 3.9.16 Define ICU\_SET\_CLOCK\_MODE\_ID

API service ID for Icu\_SetClockMode function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_SET_CLOCK_MODE_ID 0x7BU`

### 3.9.17 Define ICU\_SETACTIVATIONCONDITION\_ID

API service ID for Icu\_SetActivationCondition function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_SETACTIVATIONCONDITION_ID 0x05U`

### 3.9.18 Define ICU\_SETMODE\_ID

API service ID for Icu\_SetMode function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_SETMODE_ID 0x02U`

### 3.9.19 Define ICU\_STARTSIGNALMEASUREMENT\_ID

API service ID for Icu\_StartSignalMeasurement function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_STARTSIGNALMEASUREMENT_ID 0x13U`

### 3.9.20 Define ICU\_STARTTIMESTAMP\_ID

API service ID for Icu\_StartTimestamp function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_STARTTIMESTAMP_ID 0x09U`

### 3.9.21 Define ICU\_STOPSIGNALMEASUREMENT\_ID

API service ID for Icu\_StopSignalMeasurement function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_STOPSIGNALMEASUREMENT_ID 0x14U`

### 3.9.22 Define ICU\_STOPTIMESTAMP\_ID

API service ID for Icu\_StopTimestamp function.

Parameters used when raising an error/exception

**Definition:** `#define ICU_STOPTIMESTAMP_ID 0x0AU`

### 3.9.23 Define ICU\_E\_ALREADY\_INITIALIZED

API Icu\_Init service called when the ICU driver and the Hardware are already initialized.

**Definition:** `#define ICU_E_ALREADY_INITIALIZED 0x17U`

### 3.9.24 Define ICU\_E\_BUSY\_OPERATION

API service Icu\_SetMode is called while a running operation.

**Definition:** `#define ICU_E_BUSY_OPERATION 0x16U`

### 3.9.25 Define ICU\_E\_EDGECOUNTING\_OVERFLOW

API Icu\_GetEdgeNumbers service called when the Counter rolls over.

**Definition:** `#define ICU_E_EDGECOUNTING_OVERFLOW 0x18U`

### 3.9.26 Define ICU\_E\_MEASUREMENT\_OVERFLOW

API Icu\_GetTimeElapsed service called when the Time elapsed overflows.

**Definition:** `#define ICU_E_MEASUREMENT_OVERFLOW 0x1AU`

### 3.9.27 Define ICU\_E\_NOT\_STARTED

API service Icu\_StopTimestamp called on a channel which was not started or already stopped.

**Definition:** `#define ICU_E_NOT_STARTED 0x15U`



### 3.9.28 Define ICU\_E\_PARAM\_ACTIVATION

API service used with an invalid or not feasible activation.

**Definition:** `#define ICU_E_PARAM_ACTIVATION 0x0CU`

### 3.9.29 Define ICU\_E\_PARAM\_BUFFER\_PTR

API service used with an invalid application-buffer pointer.

**Definition:** `#define ICU_E_PARAM_BUFFER_PTR 0x0DU`

### 3.9.30 Define ICU\_E\_PARAM\_BUFFER\_SIZE

API service used with an invalid buffer size.

**Definition:** `#define ICU_E_PARAM_BUFFER_SIZE 0x0EU`

### 3.9.31 Define ICU\_E\_PARAM\_CHANNEL

API service used with an invalid channel identifier or channel was not configured for the functionality of the calling API.

**Definition:** `#define ICU_E_PARAM_CHANNEL 0x0BU`

### 3.9.32 Define ICU\_E\_PARAM\_CLOCK\_MODE

API Icu\_SetClockMode service called with wrong parameter.

**Definition:** `#define ICU_E_PARAM_CLOCK_MODE 0x7AU`

### 3.9.33 Define ICU\_E\_PARAM\_CONFIG

API Icu\_Init service called with wrong parameter.

**Definition:** `#define ICU_E_PARAM_CONFIG 0x0AU`

### 3.9.34 Define ICU\_E\_PARAM\_MODE

API service Icu\_SetMode used with an invalid mode.

**Definition:** `#define ICU_E_PARAM_MODE 0x0FU`

### 3.9.35 Define ICU\_E\_TIMESTAMP\_OVERFLOW

API Icu\_GetTimestampIndex service called when the Time stamp count overflows.

**Definition:** `#define ICU_E_TIMESTAMP_OVERFLOW 0x19U`

### 3.9.36 Define ICU\_E\_UNINIT

API service used without module initialization.

**Definition:** `#define ICU_E_UNINIT 0x14U`

## 3.10 Symbolic Names DISCLAIMER

All containers having the symbolic name tag set as true in the Autosar schema will generate defines like:

```
#define <Container_Short_Name> <Container_ID>
```

For this reason it is forbidden to duplicate the name of such containers across the MCAL configuration, or to use names that may trigger other compile issues (e.g. match existing `#ifdefs` arguments).

## 3.11 Configuration Parameters

As per the AUTOSAR specification the driver has two types of configurations parameters: **Pre-Compile** parameters and **Post-Build** parameters.

These can be selected using “IMPLEMENTATION\_CONFIG\_VARIANT”

Pre-Compile parameters are stored in the file "Icu\_Cfg.h" and "Icu\_Cfg.c". Post-Build parameters are stored in the file "Icu\_PBcfg.c".


The files to be used for different configuration types are listed below:

1. **Variant PC:** Icu\_Cfg.h, Icu\_Cfg.c
2. **Variant PB:** Icu\_Cfg.h, Icu\_PBcfg.c
3. **Variant LT:** Not Applicable

A section for **Icu\_PBcfg.c** file is needed in linker file to place the post build configuration in desired location. Please refer to section-8 of AUTOSAR\_SWS\_C\_ImplementationRules file for complete details on configuration types.

### 3.11.1 Plugin interface

The following picture gives an example of configuration screen for all ICU parameters in Tresos® Studio configuration tool.



**Figure 3-1. Tresos Plugin snapshot for IcuGeneral form**

#### NOTE

If pre-compile variant is preferred,

Configuration Parameters

- IMPLEMENTATION\_CONFIG\_VARIANT in Tresos GUI should be selected as “VariantPreCompile” as shown below





Figure 3-2. Tresos Plugin snapshot for IcuConfigurationVariant form

The following picture gives an example of configuration screen for all ICU configuration set.



Figure 3-3. Tresos Plugin snapshot for IcuConfigsSet form

The following picture gives an example of configuration screen for General configuration for a specific set



**Figure 3-4. Tresos Plugin snapshot for Icu\_MaxChannel form for a specific set**

The following picture gives an example for IcuChannel container



**Figure 3-5. Tresos Plugin snapshot for Icu\_Channel container**

The following picture gives an example for a configuration screen of an Icu channel

IcuChannel

Name
IcuChannel\_0

General

IcuChannelId (0 -> 24)
0

IcuHwChannel
EMIOS\_0\_CH\_0

IcuEmiosFreeze
☐

IcuEmiosPrescaler
EMIOS\_PRESCALER\_DIVIDE\_1

IcuEmiosPrescaler\_Alternate
EMIOS\_PRESCALER\_DIVIDE\_1

IcuEmiosDigitalFilter
EMIOS\_DIGITAL\_FILTER\_BYPASSED

IcuEmiosBusSelect
EMIOS\_BUS\_INTERNAL\_COUNTER

IcuDefaultStartEdge
ICU\_RISING\_EDGE

IcuMeasurementMode\*
ICU\_MODE\_SIGNAL\_MEASUREMENT

IcuUserModeForDutycycle
SAIC

IcuOverflowNotification
NULL\_PTR

IcuWakeupCapability
☐

IcuEdgeCounterMeasurement

IcuEdgeCounterMeasurement

IcuSignalEdgeDetection

IcuSignalEdgeDetection

IcuSignalNotification
NULL\_PTR

IcuSignalMeasurement

IcuSignalMeasurement

IcuSignalMeasurementProperty
ICU\_DUTY\_CYCLE

IcuTimestampMeasurement

IcuTimestampMeasurement

IcuTimestampMeasurementProperty
ICU\_LINEAR\_BUFFER

IcuTimestampNotification
NULL\_PTR

IcuWakeup

IcuWakeup

IcuChannelWakeupInfo

Figure 3-6. Tresos Plugin snapshot for Icu\_Channel form


### 3.11.2 Pre-Compile Parameters

Pre-Compile parameters, their possible values and meaning are described in the following text. Pre-Compile parameters are implemented as preprocessor defines.

#### NOTE

If pre-compile variant is preferred, then:

- IMPLEMENTATION\_CONFIG\_VARIANT in Tresos GUI should be selected as “VariantPreCompile” as shown below



**Figure 3-7. Tresos Plugin snapshot for IcuConfigurationVariant form**

- Icu\_Cfg.c should be compiled
- Icu\_PBcfg.c should not be compiled

#### 3.11.2.1 IcuMaxChannel

**Table 3-36. IcuMaxChannel**

<b>Description</b>	Number of configured icu channels
<b>Class</b>	Autosar Parameter
<b>Range</b>	0-40
<b>Default</b>	0
<b>Source File</b>	Icu_PBcfg.c
<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ConfigType, ICU_CONST) IcuConfigSet_0 = {     12, /* The number of channels configured*/     Icu_InitPBChannel_0,     Icu_InitPBChannelIndex_0,     Icu_ChannelId_0,     Icu_InitPBHWMap_0,     Icu_InitPBHWKMap_0 }; </pre>

### 3.11.2.2 IcuIndex

**Table 3-37. IcuIndex**

<b>Description</b>	This parameter Specifies the InstanceId of this module instance. If only one instance is present it shall have the Id 0.  <b>NOTE:</b> In current implementation this parameter is not used.
<b>Class</b>	Autosar Parameter
<b>Range</b>	0-255
<b>Default</b>	0
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	<code>#define ICU_INDEX &lt;0-255&gt;</code>
<b>NOTE</b>	<i>This parameter is not used in the current implementation</i>

### 3.11.2.3 IcuDevErrorDetect

**Table 3-38. IcuDevErrorDetect**

<b>Description</b>	Switches the Development Error Detection and Notification ON or OFF
<b>Class</b>	Autosar Parameter
<b>Range</b>	True,false
<b>Default</b>	True
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	<code>#define ICU_DEV_ERROR_DETECT &lt;STD_OFF, STD_ON&gt;</code>

### 3.11.2.4 IcuReportWakeupSource

**Table 3-39. IcuReportWakeupSource**

<b>Description</b>	Switch for enabling Wakeup source reporting.
<b>Class</b>	Autosar Parameter
<b>Range</b>	True, False
<b>Default</b>	True
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	<code>#define ICU_REPORT_WAKEUP_SOURCE &lt;STD_OFF, STD_ON&gt;</code>



### 3.11.2.5 IcuEnableDualClockMode

**Table 3-40. IcuEnableDualClockMode**

<b>Description</b>	Adds / removes the service Icu_SetClockMode () from the code.
<b>Class</b>	Non Autosar Parameter
<b>Range</b>	True,false
<b>Default</b>	False
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	#define ICU_DUAL_CLOCK_MODE <STD_OFF, STD_ON>

### 3.11.2.6 IcuDelInitApi

**Table 3-41. IcuDelInitApi**

<b>Description</b>	Adds / removes the service Icu_DelInit() from the code
<b>Class</b>	Autosar Parameter
<b>Range</b>	True,false
<b>Default</b>	True
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	#define ICU_DE_INIT_API <STD_OFF, STD_ON>

### 3.11.2.7 IcuDisableWakeupApi

**Table 3-42. IcuDisableWakeupApi**

<b>Description</b>	Adds / removes the service Icu_DisableWakeup () from the code.
<b>Class</b>	Autosar Parameter
<b>Range</b>	True, False
<b>Default</b>	True
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	#define ICU_DISABLE_WAKEUP_API<STD_OFF, STD_ON>

### 3.11.2.8 IcuEdgeCountApi

**Table 3-43. IcuEdgeCountApi**

<b>Description</b>	Adds / removes all services related to the edge counting functionality as listed below, from the code: Icu_ResetEdgeCount(), Icu_EnableEdgeCount(), Icu_DisableEdgeCount(), Icu_GetEdgeNumbers()
--------------------	--

*Table continues on the next page...*

**Table 3-43. IcuEdgeCountApi (continued)**

<b>Class</b>	Autosar Parameter
<b>Range</b>	True , False
<b>Default</b>	True
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	#define ICU_EDGE_COUNT_API <STD_OFF, STD_ON>

### 3.11.2.9 IcuEnableWakeupApi

**Table 3-44. IcuEnableWakeupApi**

<b>Description</b>	Adds / removes the service Icu_EnableWakeup () from the code.
<b>Class</b>	Autosar Parameter
<b>Range</b>	True,false
<b>Default</b>	True
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	#define ICU_ENABLE_WAKEUP_API <STD_OFF, STD_ON>

### 3.11.2.10 IcuGetDutyCycleValuesApi

**Table 3-45. IcuGetDutyCycleValuesApi**

<b>Description</b>	Adds / removes the service Icu_GetDutyCycleValues () from the code. If IcuSignalMeasurementApi == OFF this switch should be set to OFF
<b>Class</b>	Autosar Parameter
<b>Range</b>	True, False
<b>Default</b>	True
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	#define ICU_GET_DUTY_CYCLE_VALUES_API <STD_OFF, STD_ON>

### 3.11.2.11 IcuGetInputStateApi

**Table 3-46. IcuGetInputStateApi**

<b>Description</b>	Adds / removes the service Icu_GetInputState () from the code.
<b>Class</b>	Autosar Parameter
<b>Range</b>	True,false
<b>Default</b>	True

*Table continues on the next page...*

**Table 3-46. IcuGetInputStateApi (continued)**

<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	<code>#define ICU_GET_INPUT_STATE_API &lt;STD_OFF, STD_ON&gt;</code>

### 3.11.2.12 IcuGetTimeElapsedApi

**Table 3-47. IcuGetTimeElapsedApi**

<b>Description</b>	Adds / removes the service Icu_GetTimeElapsed () from the code. If IcuSignalMeasurementApi == OFF this switch should be set to OFF
<b>Class</b>	Autosar Parameter
<b>Range</b>	True,false
<b>Default</b>	True
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	<code>#define ICU_GET_TIME_ELAPSED_API &lt;STD_OFF, STD_ON&gt;</code>

### 3.11.2.13 IcuGetVersionInfoApi

**Table 3-48. IcuGetVersionInfoApi**

<b>Description</b>	Adds / removes the service Icu_GetVersionInfo () from the code.
<b>Class</b>	Autosar Parameter
<b>Range</b>	True,false
<b>Default</b>	True
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	<code>#define ICU_GET_VERSION_INFO_API &lt;STD_OFF, STD_ON&gt;</code>

### 3.11.2.14 IcuSetModeApi

**Table 3-49. IcuSetModeApi**

<b>Description</b>	Adds / removes the service Icu_SetMode() from the code
<b>Class</b>	Autosar Parameter
<b>Range</b>	True,false
<b>Default</b>	True
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	<code>#define ICU_SET_MODE_API &lt;STD_OFF, STD_ON&gt;</code>

### 3.11.2.15 IcuTimestampApi

**Table 3-50. IcuTimestampApi**

<b>Description</b>	Adds / removes all services related to the timestamping functionality as listed below from the code: Icu_StartTimestamp(), Icu_StopTimestamp(), Icu_GetTimestampIndex()
<b>Class</b>	Autosar Parameter
<b>Range</b>	True, False
<b>Default</b>	True
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	<code>#define ICU_TIMESTAMP_API &lt;STD_OFF, STD_ON&gt;</code>

### 3.11.2.16 IcuSignalMeasurementApi

**Table 3-51. IcuSignalMeasurementApi**

<b>Description</b>	Adds / removes the services: Icu_StartSignalMeasurement () and Icu_StopSignalMeasurement ().
<b>Class</b>	Autosar Parameter
<b>Range</b>	True,false
<b>Default</b>	True
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	<code>#define ICU_SIGNAL_MEASUREMENT_API &lt;STD_OFF, STD_ON&gt;</code>

### 3.11.2.17 IcuChannelId

**Table 3-52. IcuChannelId**

<b>Description</b>	Channel Id of the ICU channel.
<b>Class</b>	Autosar Parameter
<b>Range</b>	0-40
<b>Default</b>	0
<b>Source File</b>	Icu_PBCfg.c
<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ConfigType, ICU_CONST) IcuConfigSet_0 = {     1, /* The number of channels configured*/     Icu_InitPBChannel_0,     Icu_InitPBChannelIndex_0,     <b>Icu_ChannelId_0,</b>     Icu_InitPBHWMap_0,     Icu_InitPBHWKMap_0 }; </pre>

### 3.11.2.18 IcuHwChannel

**Table 3-53. IcuHwChannel**

<b>Description</b>	Channel Id of the ICU channel.
<b>Class</b>	Autosar Parameter
<b>Range</b>	EMIOS_0_CH[0-31], EMIOS_1_CH[0-31], IRQ[0-23], WKPU[0-28]
<b>Default</b>	EMIOS_0_CH_0
<b>Source File</b>	Icu_Cfg.c, Icu_PBCfg.c
<b>Source Representation</b>	<pre> <b>CONST</b>(Icu_ChannelType,ICU_VAR) Icu_ChannelId_0[13]= { ICU_IRQ_0,   ICU_WKUP_4,   ICU_IRQ_2,   ICU_EMIOS_0_CH_9,   ICU_EMIOS_0_CH_8,   ICU_EMIOS_1_CH_16,   ICU_EMIOS_1_CH_23,   ICU_EMIOS_0_CH_16,   ICU_EMIOS_0_CH_10,   ICU_EMIOS_0_CH_11,   ICU_EMIOS_1_CH_17,   ICU_WKUP_10,   ICU_WKUP_3 }; </pre>

### 3.11.2.19 icuoverflownotificationapi

**Table 3-54. Icuoveflownotificationapi**

<b>Description</b>	Adds / removes the service Overflow Notification functionality
<b>Class</b>	Autosar Parameter
<b>Range</b>	True,false
<b>Default</b>	False
<b>Source File</b>	Icu_Cfg.h
<b>Source Representation</b>	<pre>#define ICU_OVERFLOW_NOTIFICATION_API &lt;STD_OFF, STD_ON&gt;</pre>

### **3.11.3 Link Time parameters**


N/A

### **3.11.4 Post - Build Parameters**

Post-Build parameters, their possible values and their meaning are described in the following text. The Post-Build parameters are implemented as constant structures and arrays stored in flash memory of the ICU.



The configuration screen for ICU postbuild parameters in Tresos® Studio Configuration Tool is given below:



**IcuChannel**



Name  IcuChannel\_0



---


**General**



IcuChannelId (0 -> 24)  0 



IcuHwChannel  EMIOS\_0\_CH\_0 



IcuEmiosFreeze  ☐ 



IcuEmiosPrescaler  EMIOS\_PRESCALER\_DIVIDE\_1 



IcuEmiosPrescaler\_Alternate  EMIOS\_PRESCALER\_DIVIDE\_1


IcuEmiosDigitalFilter  EMIOS\_DIGITAL\_FILTER\_BYPASSED 



IcuEmiosBusSelect  EMIOS\_BUS\_INTERNAL\_COUNTER 

IcuDefaultStartEdge  ICU\_RISING\_EDGE 

IcuMeasurementMode\*  ICU\_MODE\_SIGNAL\_MEASUREMENT 


IcuUserModeForDutycycle  SAIC 

IcuOverflowNotification  NULL\_PTR

IcuWakeupCapability  ☐ 


---


**IcuEdgeCounterMeasurement**

 IcuEdgeCounterMeasurement

---


**IcuSignalEdgeDetection**



 IcuSignalEdgeDetection

IcuSignalNotification  NULL\_PTR

---


**IcuSignalMeasurement**


 IcuSignalMeasurement


IcuSignalMeasurementProperty  ICU\_DUTY\_CYCLE 

---

**IcuTimestampMeasurement**


 IcuTimestampMeasurement

IcuTimestampMeasurementProperty  ICU\_LINEAR\_BUFFER

IcuTimestampNotification  NULL\_PTR

---

**IcuWakeup**

 IcuWakeup



IcuChannelWakeupInfo  

Figure 3-8. Tresos Plugin snapshot for Icu\_Channel form

### 3.11.4.1 Icu\_ParamType

Icu\_ParamType is defined as a uint32. The Icu\_ParamValue contains combined bit fields for initialization options, for different registers. Definitions are provided in Icu\_cfg.h.

The table below depicts the Icu\_ParamType values.

**Table 3-55. Icu\_ParamType Values**

Definition	Description
ICU_FALLING_EDGE	Initialization option for eMIOS, IRQ and channels. It is the Default start edge when falling edge is selected.
ICU_RISING_EDGE	Initialization option for eMIOS, IRQ and channels. It is the Default start edge when rising edge is selected.
ICU_BOTH_EDGES	Initialization option for eMIOS, IRQ and channels. It is the Default start edge when both edges are selected.
ICU_WAKEUP_CAPABLE	Initialization option to specify the channel as wakeup capable. This works for eMIOS, IRQ and channels
EMIOS_BUS_A	Initialization option to specify that the channel runs off Timer Bus A. Hardware Dependent Definition. DO NOT CHANGE.
EMIOS_BUS_DIVERSE	Initialization option to specify that the channels 0 to 7 run off Timer Bus B, Channels 8 to 15 run off from Timer bus C. Hardware Dependent Definition. DO NOT CHANGE.
EMIOS_BUS_INTERNAL_COUNTER	Initialization option to specify that the channel runs off its own internal time base. Hardware Dependent Definition. DO NOT CHANGE.
EMIOS_DIGITAL_FILTER_BYPASSED	Initialization option to disable the filter. Hardware Dependent Definition. DO NOT CHANGE.
EMIOS_DIGITAL_FILTER_02	Initialization option to set the filter to 2 clocks. Hardware Dependent Definition. DO NOT CHANGE.
EMIOS_DIGITAL_FILTER_04	Initialization option to set the filter to 4 clocks. Hardware Dependent Definition. DO NOT CHANGE.
EMIOS_DIGITAL_FILTER_08	Initialization option to set the filter to 8 clocks. Hardware Dependent Definition. DO NOT CHANGE.
EMIOS_DIGITAL_FILTER_16	Initialization option to set the filter to 16 clocks. Hardware Dependent Definition. DO NOT CHANGE.
EMIOS_PRESCALER_DIVIDE_1	Initialization option to set the channel prescale value to 1. Only applies to channels configured to run off the internal counter bus. Hardware Dependent Definition. DO NOT CHANGE.
EMIOS_PRESCALER_DIVIDE_2	Initialization option to set the channel prescale value to 2. Only applies to channels configured to run off the internal counter bus. Hardware Dependent Definition. DO NOT CHANGE.
EMIOS_PRESCALER_DIVIDE_3	Initialization option to set the channel prescale value to 3. Only applies to channels configured to run off the internal counter bus. Hardware Dependent Definition. DO NOT CHANGE.
EMIOS_PRESCALER_DIVIDE_4	Initialization option to set the channel prescale value to 4. Only applies to channels configured to run off the internal counter bus. Hardware Dependent Definition. DO NOT CHANGE.

*Table continues on the next page...*



**Table 3-55. Icu\_ParamType Values (continued)**

EMIOS_FREEZE_ENABLE	Initialization option to enable freeze mode for the channel. If this option is not specified, freeze mode will be disabled when Icu_Init is called for the channel. Hardware Dependent Definition. DO NOT CHANGE.
SIUL_INT_FILTER_ENABLE	Initialization option to enable IRQ filter
WKPU_INT_FILTER_ENABLE	Initialization option for analog filter on the corresponding interrupt pads to filter out glitches on the inputs
IcuEXT_ISR_IFMCDigitalFilter	Initialization option to configure the filter counter associated with each digital glitch filter.
WKPU_PULLUP_ENABLE	Initialization option to enable a pullup on the corresponding interrupt pads to pull an unconnected wakeup/interrupt input to a value of '1'

### 3.11.4.2 IcuEmiosFreeze

**Table 3-56. IcuEmiosFreeze**

<b>Description</b>	If selected eMIOS channel registers are freezed in debug mode.
<b>Class</b>	Implementation specific Non-Autosar parameter
<b>Range</b>	True,false
<b>Default</b>	True
<b>Source File</b>	Icu_PBcfg.c
<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         ((ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)         (EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)         ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )            (EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)           (EMIOS_BUS_INTERNAL_COUNTER (1s)         ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         ICU_MODE_SIGNAL_MEASUREMENT,         ICU_DUTY_CYCLE,         NULL_PTR,         0U     } } </pre>

### 3.11.4.3 IcuEmiosPrescaler

**Table 3-57. IcuEmiosPrescaler**

<b>Description</b>	If an eMIOS channel is being used, this configures the prescaler value for the specific channel.
--------------------	--

*Table continues on the next page...*

**Table 3-57. IcuEmiosPrescaler (continued)**

<b>Class</b>	Implementation specific Non-Autosar parameter
<b>Range</b>	EMIOS_PRESCALER_DIVIDE_1, EMIOS_PRESCALER_DIVIDE_2, EMIOS_PRESCALER_DIVIDE_3, EMIOS_PRESCALER_DIVIDE_4
<b>Default</b>	EMIOS_PRESCALER_DIVIDE_1
<b>Source File</b>	Icu_PBcfg.c
<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         ((ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)            (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)          (EMIOS_PRESCALER_DIVIDE_1 (1s)           ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)           ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )            (EMIOS_DIGITAL_FILTER_BYPASSED (1s)           ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)            (EMIOS_BUS_INTERNAL_COUNTER (1s)           ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         ICU_MODE_SIGNAL_MEASUREMENT,         ICU_DUTY_CYCLE,         NULL_PTR,         0U     } } </pre>

### 3.11.4.4 IcuEmiosPrescaler\_Alternate

**Table 3-58. IcuEmiosPrescaler\_Alternate**

<b>Description</b>	this parameter configures the clock divider value for the internal prescaler of specific Unified Channel.
<b>Class</b>	Autosar Parameter
<b>Range</b>	EMIOS_PRESCALER_DIVIDE_1-EMIOS_PRESCALER_DIVIDE_4
<b>Default</b>	EMIOS_PRESCALER_DIVIDE_1
<b>Source File</b>	Icu_PBcfg.c

*Table continues on the next page...*

**Table 3-58. IcuEmiosPrescaler\_Alternate (continued)**

<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         ((Icu_ParamType)ICU_WAKEUP_CAPABLE (1s) ICU_WAKEUP_SHIFT)           (ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)           (EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)         ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )           (EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)           (EMIOS_BUS_INTERNAL_COUNTER (1s)         ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         ICU_MODE_SIGNAL_MEASUREMENT,         ICU_DUTY_CYCLE,         NULL_PTR,         0U     } } </pre>
------------------------------	--

### 3.11.4.5 IcuEmiosDigitalFilter

**Table 3-59. IcuEmiosDigitalFilter**

<b>Description</b>	If a eMIOS channel is being used this option is active, possible values are: 0 (Bypassed), 2, 4, 8, 16 FLT_Clock periods.
<b>Class</b>	Implementation specific Non-Autosar parameter
<b>Range</b>	EMIOS_DIGITAL_FILTER_BYPASSED, EMIOS_DIGITAL_FILTER_02, EMIOS_DIGITAL_FILTER_04, EMIOS_DIGITAL_FILTER_08, EMIOS_DIGITAL_FILTER_16
<b>Default</b>	EMIOS_DIGITAL_FILTER_BYPASSED
<b>Source File</b>	Icu_PBcfg.c
<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         ((ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)         (EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)         ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )           (EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)           (EMIOS_BUS_INTERNAL_COUNTER (1s)         ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         ICU_MODE_SIGNAL_MEASUREMENT,         ICU_DUTY_CYCLE,         NULL_PTR,         0U     } } </pre>

### 3.11.4.6 IcuEmiosBusSelect

**Table 3-60. IcuEmiosBusSelect**

<b>Description</b>	Selects the counter used with the unified channel.
<b>Class</b>	Autosar Parameter
<b>Range</b>	EMIOS_BUS_A, EMIOS_BUS_DIVERSE, EMIOS_BUS_INTERNAL_COUNTER,
<b>Default</b>	EMIOS_BUS_INTERNAL_COUNTER (if applicable) or EMIOS_BUS_A
<b>Source File</b>	Icu_PBcfg.c
<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         ((ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)         (EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)         ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )           (EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)           (<b>EMIOS_BUS_INTERNAL_COUNTER (1s)</b>         <b>ICU_EMIOS_BUS_SELECT_PARAM_SHIFT</b>)),         ICU_MODE_SIGNAL_MEASUREMENT,         ICU_DUTY_CYCLE,         NULL_PTR,         0U     } } </pre>

### 3.11.4.7 IcuDefaultStartEdge

**Table 3-61. IcuDefaultStartEdge**

<b>Description</b>	Configures the default-activation-edge which shall be used for this channel if there was no activation-edge configured by the call of service Icu_SetActivationCondition (). In case the Measurement Mode is "SignalMeasurement" and the properties DutyCycle or Period are set, the edge configured here is used as Default Period Start Edge.
<b>Class</b>	Autosar Parameter
<b>Range</b>	IcuRisingEdge, IcuFallingEdge, IcuBothEdges
<b>Default</b>	IcuRisingEdge
<b>Source File</b>	Icu_PBcfg.c

*Table continues on the next page...*

**Table 3-61. IcuDefaultStartEdge (continued)**

<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         ((ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)         (EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)         ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )           (EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)           (EMIOS_BUS_INTERNAL_COUNTER (1s)         ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         ICU_MODE_SIGNAL_MEASUREMENT,         ICU_DUTY_CYCLE,         NULL_PTR,         0U     } } </pre>
------------------------------	---

### 3.11.4.8 IcuMeasurementMode

**Table 3-62. IcuMeasurementMode**

<b>Description</b>	Configures the measurement mode of this channel.
<b>Class</b>	Autosar Parameter
<b>Range</b>	IcuSignalEdgeDetection, IcuEdgeCounter, IcuSignalMeasurement, IcuTimestamp
<b>Default</b>	IcuSignalEdgeDetection
<b>Source File</b>	Icu_PBcfg.c
<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         ((ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)         (EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)         ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )           (EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)           (EMIOS_BUS_INTERNAL_COUNTER (1s)         ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         <b>ICU_MODE_SIGNAL_MEASUREMENT,</b>         ICU_DUTY_CYCLE,         NULL_PTR,         0U     } } </pre>

### 3.11.4.9 IcuUserModeForDutycycle

**Table 3-63. IcuUserModeForDutycycle**

<b>Description</b>	Selection of the signal measurement mode when IcuSignalMeasurementProperty is ICU_DUTY_CYCLE.  <b>NOTE:</b> This parameter will be enabled in configuration only when IcuSignalMeasurementProperty is ICU_DUTY_CYCLE.
<b>Class</b>	Non Autosar Parameter
<b>Range</b>	IPWM, SAIC
<b>Default</b>	SAIC
<b>Source File</b>	Icu_PBcfg.c
<b>Source Representation</b>	The highlighted portion of the following structure:  <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         (((Icu_ParamType)ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           ((Icu_ParamType)<b>EMIOS_UC_IPWM_MODE</b> (1s)         ICU_EMIOS_UC_MODE_PARAM_SHIFT)           ((Icu_ParamType)EMIOS_FREEZE_ENABLE (1s)         ICU_EMIOS_FREEZE_PARAM_SHIFT))           ((Icu_ParamType)EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)           ((Icu_ParamType)EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIG_FILTER_PARAM_SHIFT)           ((Icu_ParamType)EMIOS_BUS_A (1s) ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         ICU_MODE_SIGNAL_MEASUREMENT,         ICU_DUTY_CYCLE,         NULL_PTR,         0U     } } </pre>

### 3.11.4.10 IcuWakeupCapability

**Table 3-64. IcuWakeupCapability**

<b>Description</b>	Boolean flag whether wake-up on this channel is supported or not.
<b>Class</b>	Autosar Parameter
<b>Range</b>	True,false
<b>Default</b>	True
<b>Source File</b>	Icu_PBcfg.c

*Table continues on the next page...*

**Table 3-64. IcuWakeupCapability (continued)**

<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         (((Icu_ParamType)ICU_WAKEUP_CAPABLE (1s) ICU_WAKEUP_SHIFT)           (ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)         (EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)         ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )           (EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)           (EMIOS_BUS_INTERNAL_COUNTER (1s)         ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         ICU_MODE_SIGNAL_MEASUREMENT,         ICU_DUTY_CYCLE,         NULL_PTR,         0U     } } </pre>
------------------------------	---

### 3.11.4.11 IcuSignalNotification

**Table 3-65. IcuSignalNotification**

<b>Description</b>	Notification function for signal notification.
<b>Class</b>	Autosar Parameter
<b>Range</b>	NA
<b>Default</b>	"NULL"
<b>Source File</b>	Icu_PBcfg.c
<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         (((Icu_ParamType)ICU_WAKEUP_CAPABLE (1s) ICU_WAKEUP_SHIFT)           (ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)         (EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)         ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )           (EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)           (EMIOS_BUS_INTERNAL_COUNTER (1s)         ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         ICU_MODE_SIGNAL_EDGE_DETECT,         ICU_DUTY_CYCLE,         <b>EMIOS_0_CH_0_Notification,</b>         0U     } } </pre>

### 3.11.4.12 IcuSignalMeasurementProperty

**Table 3-66. IcuSignalMeasurementProperty**

<b>Description</b>	Configures the property that could be measured in case the mode is "IcuSignalMeasurement". This property can not be changed during runtime.
<b>Class</b>	Autosar Parameter
<b>Range</b>	IcuPeriodTime, IcuDutyCycle, IcuHighTime, IcuLowTime
<b>Default</b>	IcuDutyCycle
<b>Source File</b>	Icu_PBcfg.c
<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         ((ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)         (EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)         ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )           (EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)           (EMIOS_BUS_INTERNAL_COUNTER (1s)         ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         ICU_MODE_SIGNAL_MEASUREMENT,         <b>ICU_DUTY_CYCLE</b>,         NULL_PTR,         0U     } } </pre>

### 3.11.4.13 IcuTimestampMeasurementProperty

**Table 3-67. IcuTimestampMeasurementProperty**

<b>Description</b>	Configures the handling of the buffer in case the mode is "Timestamp"
<b>Class</b>	Autosar Parameter
<b>Range</b>	IcuLinearBuffer, IcuCircularBuffer
<b>Default</b>	IcuLinearBuffer
<b>Source File</b>	Icu_PBcfg.c

*Table continues on the next page...*



**Table 3-67. IcuTimestampMeasurementProperty (continued)**

<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         (((Icu_ParamType)ICU_WAKEUP_CAPABLE (1s) ICU_WAKEUP_SHIFT)           (ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)         (EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)         ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )           (EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)           (EMIOS_BUS_INTERNAL_COUNTER (1s)         ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         ICU_MODE_TIME_STAMP,         <b>ICU_CIRCULAR_BUFFER,</b>         EMIOS_0_CH_0_Notification,         0U     } } </pre>
------------------------------	--

### 3.11.4.14 IcuTimestampNotification

**Table 3-68. IcuTimestampNotification**

<b>Description</b>	Notification function if the number of requested timestamps (Notification interval > 0) are acquired.
<b>Class</b>	Autosar Parameter
<b>Range</b>	NA
<b>Default</b>	NULL_PTR
<b>Source File</b>	Icu_PBcfg.c
<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         (((Icu_ParamType)ICU_WAKEUP_CAPABLE (1s) ICU_WAKEUP_SHIFT)           (ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)         (EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)         ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )           (EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)           (EMIOS_BUS_INTERNAL_COUNTER (1s)         ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         ICU_MODE_TIME_STAMP,         ICU_CIRCULAR_BUFFER,         <b>Timestamp1_Notification,</b>         0U     } } </pre>

### 3.11.4.15 IcuChannelWakeupInfo

**Table 3-69. IcuChannelWakeupInfo**

<b>Description</b>	If the wakeup capability is true the wakeup source referenced is transmitted to the ECU State Manager (EcuM).
<b>Class</b>	Autosar Parameter
<b>Range</b>	NA
<b>Default</b>	NA
<b>Source File</b>	Icu_PBcfg.c
<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         (((Icu_ParamType)ICU_WAKEUP_CAPABLE (1s) ICU_WAKEUP_SHIFT)           (ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)         (EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)         ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )           (EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)           (EMIOS_BUS_INTERNAL_COUNTER (1s)         ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         ICU_MODE_TIME_STAMP,         ICU_CIRCULAR_BUFFER,         Icu_SignalNotification_IRQ_1_User,         0U     } } </pre>

### 3.11.4.16 IcuOverflowNotification

**Table 3-70. IcuOverflowNotification**

<b>Description</b>	<p>Icu Overflow Notification Handle. In order to activate this field you have to:</p> <ul style="list-style-type: none"> <li>• enable <i>IcuOverflowNotificationApi</i>,</li> <li>• choose one of the modes: <ul style="list-style-type: none"> <li>• ICU_MODE_EDGE_COUNTER,</li> <li>• ICU_MODE_SIGNAL_MEASUREMENT,</li> <li>• ICU_MODE_TIMESTAMP</li> </ul> </li> </ul>
<b>Class</b>	Autosar Parameter
<b>Range</b>	NA
<b>Default</b>	"NULL_PTR"
<b>Source File</b>	Icu_PBcfg.c

*Table continues on the next page...*

**Table 3-70. IcuOverflowNotification (continued)**

<b>Source Representation</b>	<p>The highlighted portion of the following structure:</p> <pre> CONST(Icu_ChannelConfigType, ICU_CONST) Icu_InitPBChannel_0[1] = {     {         ((ICU_RISING_EDGE (1s) ICU_EDGE_PARAM_SHIFT)           (EMIOS_FREEZE_ENABLE (1s) ICU_EMIOS_FREEZE_PARAM_SHIFT)         (EMIOS_PRESCALER_DIVIDE_1 (1s)         ICU_EMIOS_PRESCALER_PARAM_SHIFT)   (EMIOS_PRESCALER_DIVIDE_2 (1s)         ICU_EMIOS_PRESC_ALT_PARAM_SHIFT )           (EMIOS_DIGITAL_FILTER_BYPASSED (1s)         ICU_EMIOS_DIGITAL_FILTER_PARAM_SHIFT)           (EMIOS_BUS_INTERNAL_COUNTER (1s)         ICU_EMIOS_BUS_SELECT_PARAM_SHIFT)),         ICU_MODE_SIGNAL_MEASUREMENT,         ICU_DUTY_CYCLE,         NULL_PTR,         0U     } } </pre>
------------------------------	---



## **How to Reach Us:**

### **Home Page:**

[www.freescale.com](http://www.freescale.com)

### **Web Support:**

<http://www.freescale.com/support>

### **USA/Europe or Locations Not Listed:**

Freescale Semiconductor  
Technical Information Center, EL516  
2100 East Elliot Road  
Tempe, Arizona 85284  
+1-800-521-6274 or +1-480-768-2130  
[www.freescale.com/support](http://www.freescale.com/support)

### **Europe, Middle East, and Africa:**

Freescale Halbleiter Deutschland GmbH  
Technical Information Center  
Schatzbogen 7  
81829 Muenchen, Germany  
+44 1296 380 456 (English)  
+46 8 52200080 (English)  
+49 89 92103 559 (German)  
+33 1 69 35 48 48 (French)  
[www.freescale.com/support](http://www.freescale.com/support)

### **Japan:**

Freescale Semiconductor Japan Ltd.  
Headquarters  
ARCO Tower 15F  
1-8-1, Shimo-Meguro, Meguro-ku,  
Tokyo 153-0064  
Japan  
0120 191014 or +81 3 5437 9125  
[support.japan@freescale.com](mailto:support.japan@freescale.com)

### **Asia/Pacific:**

Freescale Semiconductor China Ltd.  
Exchange Building 23F  
No. 118 Jianguo Road  
Chaoyang District  
Beijing 100022  
China  
+86 10 5879 8000  
[support.asia@freescale.com](mailto:support.asia@freescale.com)

### **For Literature Requests Only:**

Freescale Semiconductor Literature Distribution Center  
1-800-441-2447 or +1-303-675-2140  
Fax: +1-303-675-2150  
[LDCForFreescaleSemiconductor@hibbertgroup.com](mailto:LDCForFreescaleSemiconductor@hibbertgroup.com)

Information in this document is provided solely to enable system and software implementers to use Freescale Semiconductors products. There are no express or implied copyright licenses granted hereunder to design or fabricate any integrated circuits or integrated circuits based on the information in this document.

Freescale Semiconductor reserves the right to make changes without further notice to any products herein. Freescale Semiconductor makes no warranty, representation, or guarantee regarding the suitability of its products for any particular purpose, nor does Freescale Semiconductor assume any liability arising out of the application or use of any product or circuit, and specifically disclaims any liability, including without limitation consequential or incidental damages. "Typical" parameters that may be provided in Freescale Semiconductor data sheets and/or specifications can and do vary in different applications and actual performance may vary over time. All operating parameters, including "Typicals", must be validated for each customer application by customer's technical experts. Freescale Semiconductor does not convey any license under its patent rights nor the rights of others. Freescale Semiconductor products are not designed, intended, or authorized for use as components in systems intended for surgical implant into the body, or other applications intended to support or sustain life, or for any other application in which failure of the Freescale Semiconductor product could create a situation where personal injury or death may occur. Should Buyer purchase or use Freescale Semiconductor products for any such unintended or unauthorized application, Buyer shall indemnify Freescale Semiconductor and its officers, employees, subsidiaries, affiliates, and distributors harmless against all claims, costs, damages, and expenses, and reasonable attorney fees arising out of, directly or indirectly, any claim of personal injury or death associated with such unintended or unauthorized use, even if such claims alleges that Freescale Semiconductor was negligent regarding the design or manufacture of the part.

RoHS-compliant and/or Pb-free versions of Freescale products have the functionality and electrical characteristics as their non-RoHS-complaint and/or non-Pb-free counterparts. For further information, see <http://www.freescale.com> or contact your Freescale sales representative.

For information on Freescale's Environmental Products program, go to <http://www.freescale.com/epp>.

Freescale™ and the Freescale logo are trademarks of Freescale Semiconductor, Inc. All other product or service names are the property of their respective owners.

© 2011 Freescale Semiconductor, Inc.